



Release Note
Of
PAD² V6 Digitizer Manager
And
PAD² V6 Plot Manager

By PAD Product Development and Support Team



PAD System™ is a trademark and a system developed by:
PAD System™ International Limited. Flat A, 2/F, Cheung Wing Industrial Building,
109-115 Wo Yi Hop Road, Kwai Chung, New Territories, Hong Kong
Telephone: (852) 2370-9178
Fax: (852) 2370-9085
E-mail: padinfo@padsystem.com
Technical support: support@padsystem.com
Website: www.padsystem.com

No part of this publication and PAD System™ software may be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language in any part form by any means without the written permission of PAD System™ International Limited. Any unauthorized duplication or use of PAD System™, in whole or in part, in print, or in any other storage and retrieval system is forbidden.



目录

Digitizer Manager	4
Plot Manager	8

Digitizer Manager

Digitizer Manager 增加了两个新功能,如下.


通过广域的 IP 发送文件

1. Digitizer Manager 的数字化文件,可以发送到 Pattern Design 的广域网 IP.
请去 Pattern Design “打开数字化仪...”选项.





2. 按增加按钮,输入 IP 地址和密码.



3. 所有的数字化文件显示在工作表.



设置设备名称和密码

1. 在选择→连接设置...项目允许设置用户密码.
客户从纸样并给出用户账户密码.

连接设置

IP地址: 180.166.25.42

[按此验证广域网IP地址](#)

端口: 10118

设备名称: PAD Digitizer Table

密码:

确定 取消

密码: 给密码身份的用户账户.

2. 在Pattern Design “打开数字化仪...”, 将出现一个对话框:

数字化仪报表

数字化仪	状态	档案数	工作目录
PAD Digitizer Table	啟用安全模式		

并入当前档案


增加 删除 确定 取消

3. 启用安全模式状态栏.

请双击选定的账号并输入密码.



4. 按确定按钮.所有的文件显示如下. 所选账户状态更改登陆成功.





Plot Manager



增加...

增加...项目打开任何 PAD System 纸样档案和唛架档案相同的版本或更低版本. 选定的文件只读和打开对话框,允许您选择想要的信息并绘制.

暂停...

选择文件并按暂停键,将选定的文件改变现状,停下来.